26. EasyPrinter


This chapter explains the setup steps of EasyPrinter.

26.1.	Overview	
26.2.	Using EasyPrinter as a Printer Server	
26.3.	Using EasyPrinter as a Backup Sever	
26.4.	EasyPrinter Operation Guide	
26.5.	Convert Batch File	



26.1. Overview


EasyPrinter is a Win32 application and can only run on MS Windows 7 SP1 / 8 / 10. It enables HMI to output screen hardcopies to a remote PC via Ethernet. The following explains how to use EasyPrinter.



Here are some advantages of using EasyPrinter:

- EasyPrinter provides two modes of hardcopy output: [Print Out] and [Save to File]. Users can use either or both modes.
- Since EasyPrinter runs on MS Windows system, it supports most of the printers available on the market.
- Multiple HMIs can share one printer so users don't have to prepare printers for each HMI.


Additionally, EasyPrinter can also be a backup server. Users can use Backup objects on HMI to copy history files such as Data Sampling records and Event Log to a remote PC via Ethernet. Please see the following illustration:





EasyBuilder Pro V6.10.01

26.2. Using EasyPrinter as a Printer Server



Users can make screen hardcopies with a Function Key object. The hardcopies will be transferred to the Remote Printer Server via Ethernet and then printed out.

26.2.1. Setup Procedure in EasyPrinter

In EasyPrinter's main menu, select [Options] » [Settings] and the following dialog box appears:

General	Server		
Hardcopy	Port number of the server socket:	8005	
Backup	User name: [Max. length = 12 characters]	admin	
Duckup	Password: [Max. length = 12 characters]	111111	
	Naming Convention for HMI Folder (when writing files) Use IP address Use HMI name (assign HMI name by L W9032~L W9039) Prefix: IP(Ex: IP_192.168.1.25)		
	Properties Image: Ima		

- **1.** Select [General] on the left hand side.
- 2. In [Server], set [Port number of the server socket] to "8005", [User name] to "admin" and [Password] to "111111". (These are default values.)
- 3. In [Naming Convention for HMI Folder], select [Use IP address] and enter "IP_" in the [Prefix] field.
- In [Properties], select [Minimize to system tray] check box. Select [Start EasyPrinter when I start Windows] if necessary.

Set the print out location.



EasyPrinter

Seneral	Output	
lardcopy	Print out to:	
102010-00-0	Microsoft XPS Document Writer	-
ackup	✓ Save to files in:	
	C:\Users\Janecheng\Desktop\6.02.02\SW	0

- **1.** Select [Hardcopy] on the left hand side.
- 2. Under [Output] select [Print out to] and choose a printer as the output device for screen hardcopies. (The printer shown in the image above is an example; please select an actual printer located in your network environment.)
- 3. Select [Save to files in:] and browse for the directory to save the hardcopy file.
- 4. Click [OK] to confirm the settings.
- In EasyPrinter main menu select [File] » [Enable Output] to output any incoming print request.

26.2.2. Setup Procedure in EasyBuilder Pro


The setting procedure of EasyPrinter in EasyBuilder Pro:

- **1.** Open a new project or an existing project in EasyBuilder Pro.
- 2. In EasyBuilder Pro main menu select [Home] » [System Parameters] » [Printer/Backup Server] and select [Use Remote Printer/Backup Server] check box.



Device	Model	General	System Setting	Security	Font
Extended	Memory	Printer/Bad	kup Server	e-Mail	Recipes
Note: Use E Dutput settir	-	figure PC for prin	ting screen hardcop	y and storing backup) data.
Print	er size : 💿 Orig	jinal size	Fit to printer ma	argins	
	Margin :	0	🔶 mm		
	C) 🔿 mm	0 😤	mm	
Communicati	on settings				
IP a	ddress : 192	. 168 . 1	. 26		
	Port: 8005				
Use	r name : admin				
Pa	ssword : 11111	1			

- 3. Under [Output settings] set appropriate values for left / top / right / bottom margins. (The margins are all set to 15mm in the example.)
- 4. Under [Communication settings] fill in the [IP address] of the printer server according to the settings in EasyPrinter. Set [Port] to "8005", [User name] to "admin" and [Password] to "111111".
- **5.** Click [OK].
- In EasyBuilder Pro main menu select [Objects] » [Button], select [Function Key], select [Screen hardcopy] and set [Printer] to [MT Remote Printer/Backup Server].



- Place the Function Key object in the common window (window no. 4) so that screen hardcopies can be captured anytime when needed.
- Compile and download the project to HMI. Press the Function Key object on the screen to make a screen hardcopy.




- A PLC Control object can also be used to make screen hardcopies.
- Alarm information cannot be printed via EasyPrinter.
- EasyPrinter can only communicate with HMI via Ethernet. Please check that the HMI has appropriate network settings.



26-5

26.3. Using EasyPrinter as a Backup Sever



Backup objects can upload historical data and Operation Log to remote backup server.

26.3.1. Setup Procedure in EasyPrinter

In EasyPrinter's main menu, select [Objects] » [Settings] and the following dialog box will appear:

emote Printer	Server Settings	<u></u>	
General	Server		
Hardcopy	Port number of the server socket:	8005	
Backup	User name: [Max. length = 12 characters]	admin	
buckup	Password: [Max. length = 12 characters]	111111	
	Naming Convention for HMI Folder (when writing files) Use IP address Use HMI name (assign HMI name by L W9032-L W9039) Frefix: IP (Ex: IP 192.168.1.25)		
	IP(Ex: IP_192.160 Properties IMinimize to system tray Detailed message		
	V Start EasyPrinter when I start Window	8	
		OK Cancel	

- **1.** Select [General] on the left hand side.
- Under [Server] set [Port number of the server socket] to "8005", [User name] to "admin" and [Password] to "111111". (These are default values.)
- Under [Naming Convention for HMI Folder] select [Use IP address] and enter "IP_" in the [Prefix] field.
- 4. Under [Properties] select [Minimize to system tray]. Select [Start EasyPrinter when I start



Windows] if necessary.

Set the backup location.

General	Output
Hardcopy	Backup files in:
94. (MAR) (MAR)	C:\Users\Janecheng\Desktop\6.02.02\SW
Backup	
	When target file has existed:
	Overwrite it. (The content will be destroyed)
	Append .BAK to the file name.
	Convert Batch File
	🔽 Enable
	D:\EBPro V60202/convert2csv.def
	4
	OK Cance

- **1.** Select [Backup] on the left.
- 2. Under [Output] click the incoming history files.
- 3. Click [OK] to confirm the settings.
- 4. In the main menu, select [File] » [Enable Output] to backup data in the selected directory.

26.3.2. Setup Procedure in EasyBuilder Pro

The setup procedure of EasyPrinter in EasyBuilder Pro:

- **1.** Open a new project or an existing project in EasyBuilder Pro.
- In EasyBuilder Pro's main menu, select [Home] » [System Parameters] » [Printer/Backup Server] and select the [Use Remote Printer/Backup Server] check box.



Device	Model	General	System Settin	g Security	y Font
Extended	Memory	Printer/Bad	kup Server	e-Mail	Recipes
			ting screen hardco	py and storing bac	kup data.
Orien	tation : 🍥 Ho	rizontal 🔺	○ Vertical		
Printe	er size : 💿 Or	iginal size	Fit to printer n	nargins	
		0 (m) mm	0	nm	
Communicatio	on settings				
IP ac	ldress : 192	2 . 168 . 1	. 26		
	Port: 8005				
User	name : admir	ı			
Pas	ssword : 1111	11			

- 3. Under [Communication settings] fill in the [IP address] of the printer server according to the settings in EasyPrinter. Set the [Port] to "8005", [User name] to "admin" and [Password] to "111111". (Note: These are default values.)
- **4.** Click [OK].

Create a Backup object.

1. In EasyBuilder Pro's main menu, select [Data/History] » [Backup] and the following dialog

box appears:



lew Backup Object	— ×
General Security Shape Label	
Comment :	
Source	
© RW © RW_A	🔘 Recipe database
Historical event log	Historical data sampling
Operation log	
Backup position	
SD card	🔘 e-Mail
Remote printer/backup server	
Note : Use LW-9032~9039 to change t	the backup folder name.
server in [System Parameter][Printer/B	ackup Server] settings.
Range	terder.
	terday
Within : All (max. 90 days)	•
Trigger Mode : Touch trigger	T
*LB-9039 indicates the status of file backu	p activity (backup in process if status is ON)
OK	Cancel Help

- 2. Under [Source] select [Historical event log] (or [RW], [RW_A] if needed.)
- 3. Under [Backup position] select [Remote printer/backup server].
- 4. Under [Range] select [Today] and [All] (or other options if needed.)
- 5. Under [Trigger] select [Touch trigger].
- 6. Click [OK].
- Place the [Backup] object in the common window (window no. 4), and users will be able to make backups anytime when needed.
- *8.* Compile and download the project to HMI. Press the Backup object on the screen to make a backup of the history data.

Note

- The Backup object can also be triggered by a bit address.
- Users can arrange a Scheduler object, which turns a bit ON at the end of a week, to trigger the Backup object to automatically back up all history data.



26.4. EasyPrinter Operation Guide

The following introduces the interface and operation of EasyPrinter.

26.4.1. EasyPrinter Managing Window

EasyPrinter main menu is divided into 5 parts as shown in the following figure:

😪 Weintek MT Remote Printer Ser	ver - EasyPrinter				_	
<u>F</u> ile <u>E</u> dit <u>V</u> iew <u>O</u> ptions <u>I</u>	<u>H</u> elp					
🖨 🙆 😭 😭						
Job ID Address	Download Progress	д 🖂	Preview	Ф 🖾	Properties	д 🗵
	From	Progress				
1	2		3		4	
Logger						д 🗵
[10:16:55] Printer server is activ	e and ready for reque	ests. 5				
Ready					CAP N	UM SCRL

Area	Name	Description
1	Job List	Lists all incoming tasks, such as screen
		hardcopy and backup requests.
2	Download Progress	Shows the download progress of incoming
		requests.
3	Preview	Shows the preview image of the screen
		hardcopy task selected from [Job List].
4	Properties	Shows the information about the task
		selected from [Job List].
5	Logger	Shows the time and message information of
		events such as incoming request, incorrect
		password, etc.
6		



26.4.2. Operation Guide

The following describes the function of EasyPrinter menu items.

Menu	Description		
File	Enable Output		
	If selected, EasyPrinter processes the tasks one by one, otherwise,		
	EasyPrinter stores the tasks in memory.		
Edit	Edit		
	Edits screen hardcopy by setting [Orientation], [Scaling] and		
	[Margins].		
	Delete		
	Deletes the selected tasks permanently.		
	Select All		
	Selects all tasks from [Job List].		
View	Properties Bar		
	Shows or hide the Property Window.		
	Preview Bar		
	Shows or hide the Preview Window.		
	Download Bar		
	In [Download Progress] Window, the mode to display download		
	progress can be set by clicking the header of the [progress]		
	column as shown in the following figure:		
	Download Progress 🛛 🗣 📧		
	From Progress		
	Percentage Display Data Length Display		
	Data Length Display		
	Logger Bar		
	EasyPrinter can reserve up to 10,000 messages in Message		
	Window. If a new message comes in, the oldest message will be		
	deleted.		
Options	Please see the following page.		



EasyPrinter can only reserve up to 128 MB of task data in memory. If the memory is full, any request coming in afterwards will be rejected. Users must either operate [Enable



- The backup task is not editable.
- Edit] is available only when a task is selected.
- [Delete] is available when at least one task is selected.

The following is the detail for [Options] » [Settings]


In General Tab:

General	Server			
lardcopy	Port number of the server socket:	8005		
ackup	User name: [Max. length = 12 characters]	admin		
Juckup	Password: [Max. length = 12 characters] 1111111			
	Naming Convention for HMI Folder (when writing files) Use IP address Use HMI name (assign HMI name by L W9032~L W9039) Prefix: IP_ (Ex: IP_192.168.1.25)			
	Properties Minimize to system tray Detailed message V Start EasyPrinter when I start Windows			


Setting	Description	
Server	Port number of the server socket	
	Sets the Ethernet port number to connect the HMI. Range: 1 $^{\sim}$	
	65535. Default: 8005.	
	User name / Password	
	Sets the user name and password to let only authorized HMIs send	
	requests to EasyPrinter.	
Naming	EasyPrinter uses different folders to store files (e.g. hardcopy	
Convention	bitmap files, backup files) from different HMI. There are two ways	
for HMI	to name the folders:	
Folder	Use IP address	
	EasyPrinter names the folder as [Prefix] + [IP address] after the	
	HMI at this IP address sends request.	







In Hardcopy Tab:





Setting	Description
Output	Print out to
	EasyPrinter prints out the hardcopy result with the specified
	printers.
	Save to files in
	EasyPrinter converts the hardcopy result into a bitmap file and
	saves it in the specified directory. The bitmap files are found at:
	[Specified Path] \ [HMI Folder] \ yymmdd_hhmm.bmp
	For example, when a hardcopy request is given at 17:35:00,
	12/Jan/2009, the bitmap file will be named "090112_1735.bmp".
	And if there is another bitmap file generated within the same
	minute, it will be named "090112_1735_01.bmp" and so on.

In Backup Tab:


General	Output
Hardcopy	Backup files in:
пагасору	C:\Users\Janecheng\Desktop\6.02.02\SW @
Backup	
	When target file has existed:
	Overwrite it. (The content will be destroyed)
	Append BAK to the file name.
	Convert Batch File
	Enable
	D:\EBPro V60202/convert2csv.def
	OK Cancel

Setting	Description
Output	Backup files in:
	EasyPrinter stores the backup files to the specified
	path.
	The upper directory is the same:
	[Specified Path] \ [HMI Name] or [IP address]
	The lower directory:
	 For Event Log files:
	\ eventlog\ EL_yyyymmdd.evt
	 For Data Sampling files:
	\ datalog \ [File name of the Data Sampling] \
	yyyymmdd.dtl

	For Recipe files:
	\ recipe \ recipe.rcp or recipe_a.rcp
	 For Recipe Database:
	\ recipe \ recipe.db
	 For Operation Log:
	\ operationlog\ operationlog.db
Convert Batch File	Select [Enable] to convert the selected history file
	to .csv or .xls (Excel) format of Convert Batch Files.

Note

- System registers LW-9032 to LW-9039 can be used to specify HMI name.
- When closing EasyPrinter, the following dialog will appear.



26.5. Convert Batch File

EasyPrinter provides a conversion tool to convert the uploaded Data Sampling and Event Log history files to .csv files automatically. To do so, please select [Enable] under [Convert Batch File] to make EasyPrinter convert the history files.

In the following illustration, the conversion is actually executed by EasyConverter. EasyPrinter simply follows the criteria in Convert Batch File and activates EasyConverter with proper arguments to achieve the conversion.



Convert Batch File + EasyConverter

Note

EasyConverter is another Win32 application that converts history data into .csv or MS



Users requesting this function must ensure EasyPrinter and EasyConverter are placed in the same directory.

26.5.1. The Default Value of Convert Batch File

The following is the default Convert Batch File: convert2csv.def

Listing 1. Default Convert Batch File

1: "dtl", "EasyConverter /c \$(Pathname)"

2: "evt", "EasyConverter /c \$(Pathname)"

There are two lines in the file. Each line has two arguments separated by a comma and forms a criterion of how to process a specific type of files. The first argument stands for the extension name of the file type to be processed. The second argument stands for the command to be executed in console mode. Please note that "\$(Pathname)" is a key word to inform EasyPrinter to replace it with the real name of the converted backup file. For example, if a Data Sampling history file named 20090112.dtl is uploaded and stored, EasyPrinter will send out the following command to a console window:

1: EasyConverter /c 20090112.dtl

A file named 20090112.csv is created.

The criteria of the default Convert Batch File:

- 1. Convert all Data Sampling history files (.dtl) into .csv files.
- 2. Convert all Event Log history files (.evt) into .csv files.

Note

"\$(Pathname)" in the second argument stands for the full path name of the file. In the previous case, EasyPrinter replaces it with:
 [Specified Path] \ [HMI Folder] \ [datalog] \ [Folder name of the Data-Sampling object] \]

[Specified Path] \ [HMI Folder] \ [datalog] \ [Folder name of the Data-Sampling object] \ 20090112.dtl

- EasyPrinter interprets the Convert Batch File in line basis, that is, each line forms a criterion.
- Any two arguments should be separated by a comma.
- Every argument should be put in double quotes.
- Do not put any comma inside an argument.
- Supported parameters for batch file: \$(PathName), \$(HmiName), and \$(IP) which stand for file path, HMI name, and HMI IP address.
- When [Start EasyPrinter when I start Windows] option is selected, please add in the file path where EasyConverter is placed, which is usually the EBPro installation directory in



1: "dtl", "C:\EBPro\EasyConverter /c \$(Pathname)"	
2: "evt", "C:\EBPro\EasyConverter /c \$(Pathname)"	

For more information, see "25 Easy Converter".

26.5.2. Specialized Criteria

The specialized criterion are needed when:

- Upload file to a specific HMI, see listing 2.
- Identify the HMI by HMI name, see listing 3.
- Process differently to different Data Sampling, see listing 4.

(This can only be used for Data Sampling file with the file name "voltage".)

The 3rd argument ("*") indicates this criterion accepts the Data Sampling files that meet the

criterion from any HMI. Users can also change the 3rd argument to "192.168.1.26",

"192.168.1.*", or HMI name, etc. for narrowing the range of the target HMI.

Listing 2. Specialized Criterion for the HMI IP: 192.168.1.26

1: "dtl", "EasyConverter /c \$(Pathname)", "192.168.1.26"

Listing 3. Specialized Criterion for HMI name: Weintek_01

1: "dtl", "EasyConverter /c \$(Pathname)", "Weintek_01"

Listing 4. Specialized Creterion for Data Sampling file name: Voltage

1: "dtl", "EasyConverter /s Voltage.lgs \$(Pathname)", "*", "Voltage"

26.5.3. The Format of a Convert Batch File

The following explains the arguments in a criterion.

File TypeCommandHMI IP /Condition 1Condition 2(line)Name

File Type

This argument specifies the extension name of the uploaded file in this criterion.

(e.g. ".dtl" for Data Sampling history files, ".evt" for Event Log history files)

Command (line)

The command EasyPrinter sends to a console window if the uploaded file meets the criterion.

- HMI IP / Name
 This argument specifies the HMI that meets the criterion.
- Condition 1

This argument specifies the folder name of the Data Sampling files that meet the criterion. This is not effective to other format of files.

Condition 2
 Not used (Reserved for future use).

26.5.4. The Order of Examining Criterion

EasyPrinter examines criterion in descending order every time a file is uploaded. Once the file meets a criterion, it stops the examination and starts over for the next file. Therefore, users should place the criterion with a wider range downward in the Convert Batch File and place the more specific criteria upward. For example:

"evt", "EasyConverter /c \$(Pathname)"

"dtl", "EasyConverter /c \$(Pathname)"

"dtl", "EasyConverter /c \$(Pathname)", "192.168.1.26"

- "dtl", "EasyConverter /c \$(Pathname)", "my_HMI_01"
- "dtl", "EasyConverter /c \$(Pathname)", "my_HMI_02"
- "dtl", "EasyConverter /s Voltage.lgs \$(Pathname)", "*", "Voltage"

The correct order of examination would be: (from bottom to top)

"dtl", "EasyConverter /s Voltage.lgs \$(Pathname)", "*", "Voltage"

"dtl", "EasyConverter /c \$(Pathname)", "my_HMI_02"

"dtl", "EasyConverter /c \$(Pathname)", "my_HMI_01"

"dtl", "EasyConverter /c \$(Pathname)", "192.168.1.26"

"dtl", "EasyConverter /c \$(Pathname)"

"evt", "EasyConverter /c \$(Pathname)"

